
13. MODULE

Postures [REBA]

- Introduction
- Data
- Report
- Redesign



INTRODUCTION

Scope of application. The module titled Postures [REBA] allows you to analyze tasks that involve poor trunk, neck, upper or lower limbs postures, by means of the *REBA score*.

Contents. The positions to be analyzed for each subtask performed by the worker are selected; generally, the most frequent and/or most arduous working postures are initially chosen. Each analyzed posture requires encoding the position of the different body segments of *group A* (trunk, neck and legs) and *group B* (arms, forearms and wrists), as well as the force, type of grip and muscle activity engaged in that posture. This allows you to obtain a final *REBA score* for the risk level of musculoskeletal injury of a particular posture, which implies a certain *action level* in order to reduce that risk.

Source. The module is based on the REBA method (*Rapid Entire Body Assessment*) for postural analysis, which is applicable to a wide variety of tasks and was developed in the UK [Hignett y McAtamney, 2000].

DATA

The analysis is started by selecting the *Postures [REBA]* module in the *New task* window (Figure 1).

This opens the main window of the module (Figure 2), which shows the following:




Figure 1: Access to the Postures [REBA] module

Ergo/BV - Postures [OWAS]

Task: Riveting
 Company: VV Date: 20/01/2006
 Observations:
 Sampling interval: 24 seconds.

Subtask	POSTURES									
	Level 1		Level 2		Level 3		Level 4		TOTAL	
	Freq.	%	Freq.	%	Freq.	%	Freq.	%	Freq.	%
<input checked="" type="checkbox"/> Horizontal riveting	2	25,00	10	38,46	9	45,00	27	69,23	48	51,61
<input checked="" type="checkbox"/> Vertical riveting	6	75,00	16	61,54	11	55,00	12	30,77	45	48,39
TOTAL	8	8,60	26	27,96	20	21,51	39	41,94	93	100,00

Level 1 Level 2 Level 3 Level 4

0%
50%
100%

Signet. Photo Video Data Report Ok Cancel

Figure 2: Postures [REBA] – Main window

- **Identification.** The name of the task and company, analysis date and the observations of the evaluator are recorded.
- **Subtasks.** Each subtask is defined, the postures of which are to be analyzed. For example, Figure 2 shows a laundry task which includes the subtasks of sorting clothes, using the washer machine and the calender ironing machine. The name of each subtask is introduced by pressing the *New* button. The *Delete* button allows you to delete the subtask selected from the list and all the associated postures (asking for confirmation first). The name of a subtask can be changed by directly writing in the corresponding cell.
- **Postures.** The table below summarizes the information about the postures included in the subtask that has been previously selected. For example, Figure 2 shows three postures analyzed in the subtask of using the calender ironing machine.

Postures are managed with the buttons on the right side, the functions of which are as follows:

- *New*: it accesses the *Posture data* window to create a new posture in the selected subtask.
- *Edit*: it accesses the *Posture data* window to edit the information of the selected posture.
- *Delete*: it deletes the selected posture (asking for confirmation first).
- *Copy*: it copies the selected posture and all the associated data (it may be useful when similar postures that differ in very few data are recorded or when the risk of the posture is reduced by redesigning, as shown later). By pressing this button, the copied posture is added and the same name as the original is assigned by default (indicating that it is a copy). Then you must select this copy, edit the relevant changes and save them by pressing the *OK* button.

How to introduce the information associated with each posture is described below.

Posture data

The *Posture data* window is automatically headed by the name of the *subtask*, which includes the posture. The header of this window also records the following (Figure 3):

- **Posture.** A name must be assigned to the posture.
- **Frequency.** The frequency of the posture during the workday must be identified: *low* (occasionally), *medium* (often, but it is not the usual posture) or *high* (normal working posture). This is a purely subjective estimate of the evaluator which can be useful when prioritizing the actions required to reduce the risk of the posture.
- **Observations (posture).** The clarifications on the posture that are considered to be important should be specified.
- **Video reference.** If the task was recorded, the location of the posture in the video should be identified.

The screenshot shows the 'Postures [REBA] - Posture data' window. The title bar reads 'Ergo/IBV - Postures [REBA] - Posture data'. The window contains the following elements:

- Subtask:** Ironed
- Posture:** Store clothes on the shelf
- Frequency:** low (radio button), medium (radio button selected), high (radio button)
- Observations (posture):** (empty text field)
- Video reference:** (empty text field)
- Navigation tabs:** A - Trunk, Neck, Legs; B - Arms, Forearms, Wrists; Force, Grip, Activity; Results
- TRUNK Section:**
 - Icons: Extension > 20°, Ext. up to 20°, Upright, Flex. up to 20°, Flexion 20-60°, Flexion > 60°
 - Checkboxes: Rotation, Lateral tilt
- NECK Section:**
 - Icons: Extension, Flexion 0-20°, Flexion > 20°
 - Checkboxes: Rotation, Lateral tilt
- LEGS Section:**
 - Icons: Bilateral support, Walking, Sitting position, Sop.unilat./nest.
 - Checkboxes: Knee(s) flexion 30-60°, Knee(s) flexion > 60° (except in the sitting position)
- Buttons:** Video, Ok, Cancel

Figure 3: Postures [REBA] – Posture data (group A – trunk, neck, legs)

The posture encoding is done in different tabs of this window, as explained below.

A – Trunk, Neck, Legs (Figure 3). The position of the body segments of group A is registered with the help of diagrams.

- **Trunk.** Select one of the buttons in order to specify the trunk position:
 - Extension > 20°
 - Extension up to 20°
 - Upright
 - Flexion up to 20°
 - Flexion 20-60°
 - Flexion > 60°

Check the applicable box(es) if there is also:

- Rotation (which includes to the right or to the left)
- Lateral tilt (which includes to the right or to the left)

- **Neck.** Select one of the buttons to specify the neck position:
 - Extension
 - Flexion 0-20°
 - Flexion > 20°

Check the applicable box(es) if there is also:

- Rotation (which includes to the right or to the left)
- Lateral tilt (which includes to the right or to the left)

- **Legs.** Select one of the buttons to specify the legs position:
 - Bilateral support (standing with equal weight on both legs)
 - Walking
 - Sitting
 - Unilateral support or unstable posture (includes standing with one unsupported or slightly supported leg)

Check the applicable box(es) if there is also:

- Knee(s) flexion 30-60°
- Knee(s) flexion > 60° (except sitting)

B – Arms, Forearms, Wrists (Figure 4). The position of the body segments of group B is also encoded with the help of diagrams. You can analyze the **right** side, the **left** side, or both, by entering the data in the corresponding tab(s); (if both sides are analyzed, the program will only use the most arduous one to calculate the final risk).

- **Arm.** Select one of the buttons to specify the arm position:
 - Extension > 20°
 - Extension 20° to flexion 20°
 - Flexion 20-45°
 - Flexion 45-90°
 - Flexion > 90°

Check the applicable box(es) if there is also:

- **Arm abduction** (lateral movement away from the body)
 - **Arm rotation** (which includes the internal or external rotation about the longitudinal axis of the arm)
 - **Shoulder raised**
 - **Arm supported or in favor of gravity** (It includes the arm supported on a surface or maintaining a forced arm posture with the help of gravity due to the position of the trunk; for example, the arm “hangs” vertically while the trunk is flexed)
- **Forearm.** Select one of the buttons to specify the forearm position:
 - Flexion < 60°
 - Flexion 60-100°
 - Flexion > 100°
 - **Wrist.** Select one of the buttons to specify the wrist position:
 - Flexion/Extension 0-15°
 - Flexion/Extension > 15°

Check the applicable box(es) if there is also:

- **Rotation** (which includes pronation or supination)
- **Lateral deviation** (which includes radial or ulnar deviation)




Figure 4: Postures [REBA] – Posture data (group B – arms, forearms, wrists)

Force, Grip, Activity (Figure 5). Besides the position of the body segments, other aspects associated with the position being analyzed should also be recorded. These data are entered as explained below.

- **Force/Load.** Select one of the buttons to specify the force that is being applied or the load being handled:
 - < 5 kg
 - 5-10 kg
 - > 10 kg

Check the box if there is also:

- **Sudden or abrupt force** (which includes those forces that are abruptly applied, such as blows, shakes, etc.)

Ergo/IBV - Postures [REBA] - Posture data

Subtask: Ironed Posture: Store clothes on the self Frequency: low medium high

Observations: (posture) Video reference:

A - Trunk, Neck, Legs B - Arms, Forearms, Wrists Force, Grip, Activity Results

FORCE / LOAD

Sudden or abrupt force

<5 Kg 5-10 Kg >10 Kg

COUPLING

Good Fair Poor Unacceptable

ACTIVITY

Static (sustained > 1 minute)

Repeated (> 4 times/min, except walking)

Large and rapid postural changes or unstable base

Video Ok Cancel

Figure 5: Postures [REBA] – Posture data (force, grip, activity)

- **Grip.** Select one of the buttons to specify the type of grip of the element being handled:
 - **Good** (appropriate handle and mid-range power grip)
 - **Fair** (acceptable but not ideal hand grip, or acceptable grip if a part of the body other than the hand is used)
 - **Poor** (not acceptable hand grip, although possible)
 - **Unacceptable** (awkward and unsafe hand grip, without handles, or unacceptable grip when using another part of the body)

- **Activity.** Check the applicable box(es) if the following conditions related to muscle activity exist:
 - **Static** (one or more body parts are static; for example, they remain in the same position for more than 1 minute)
 - **Repeated** (actions that are repeated more than 4 times per minute, except walking)

- o **Large and rapid postural changes or unstable base** (the action causes significant and rapid changes in posture or the action is performed on a surface that is unstable)

Results (Figure 6). Once the posture is encoded, the last tab shows the assessment results. To do this, the program assigns a series of intermediate scores to the encoding items and finally obtains the **REBA score** that represents the risk of the posture.




Figure 6: Postures [REBA] – Results

The procedure that is applied is explained below:

- The individual scores for each segment of group A and group B are obtained using several tables of values.
- Then the combined score of group A, using Table A, and the combined score of group B using Table B are obtained (if both sides were assessed, the most difficult one is used while the other side is displayed dimmed in the corresponding cells).
- The *force/load* score is added to the resultant value of *Table A* in order to obtain *score A*.
- The *grip* score is added to the resultant value of *Table B* in order to obtain *score B*.
- *Scores A y B* are combined using *Table C* in order to obtain *score C*.
- The *activity* score is added to *score C* so as to obtain the final *REBA score*.

In each score cell, in addition to the current value, the *maximum possible value* for that cell is displayed in a small box. This data helps the potential redesign, as seen later.

Depending on the **REBA score** five possible **risk levels** are considered which, in turn, determine a particular **action level** that indicates the urgency of the ergonomic intervention (need to take action in order to reduce the risk), as shown in the following table.

REBA score	Risk level	Action level
1	Negligible	0. Not necessary
2-3	Low	1. May be necessary
4-7	Medium	2. Necessary
8-10	High	3. Necessary soon
11-15	Very high	4. Necessary NOW

Both the *REBA score* and the *risk level* have associated color codes for easy interpretation. Once they are calculated, these results are also shown in the main window of the module, together with the name and frequency of the posture (Figure 2).

REPORT

Pressing the *Report* button at the bottom of the main window opens another window where you can select the postures to be detailed in the optional part of the report (Figure 7). Although all the analyzed postures can be included, they can also be selected according to their risk level.




Figure 7: Postures [REBA] – Report (selection of the postures to be detailed)

When the report is configured, you can access the requested report by pressing the *Accept* button, which includes the following:

- **Identification.** It includes general information on the case (location where it is saved, date of analysis, name of the task, company and observations of the evaluator). You can also include an image of the task, if you have configured a video source.
- **Posture risk** (Figure 8). This section is always shown and summarizes the results for all the analyzed postures, grouped according to the subtask to which they belong. Each posture shows its name, estimated frequency and the results obtained for the *REBA score* and the *risk level*, with their color codes. At the end of this section, the interpretation table of the *REBA score* is included (with the five possible risk and action levels already mentioned).

POSTURE RISK				
Subtask	Posture	Frequency	REBA Score	Risk Level
Sorting clothes				
	Take the sack	medium	9	High
	Put the sack on the trolley	medium	3	Low
	Remove clothes from the sack	high	3	Low
Washing machine				
	Take clothes from the carriage	high	5	Medium
	Load washing machine	high	7	Medium
Ironed				
	Collect clothes	high	3	Low
	Fold clothes on the table	high	5	Medium
	Store clothes on the self	medium	10	High

REBA score interpretation		
REBA Score	Risk Level	Action Level
1	Negligible	0 - None necessary
2-3	Low	1 - May be necessary
4-7	Medium	2 - Necessary
8-10	High	3 - Necessary soon
11-15	Very high	4 - Necessary NOW

Evaluator (name and signature)

Figure 8: Postures [REBA] – Report (posture risk)

Posture detail (Figure 9). As already indicated, this section of the report is optional and will depend on the postures previously requested. Each posture is headed by its identification, that is, the subtask where it is included, the posture name, its frequency, observations and the video reference where it is located. The assessment results are then shown, which include all the items recorded in the encoding of the posture, the intermediate scores associated, and the final *REBA score* (including the maximum possible value of each cell) as well as the *risk* and *action levels* for that posture.

POSTURE DETAIL	
Subtask <input type="text" value="Ironed"/>	Posture <input type="text" value="Store clothes on the self"/>
Observations (posture) <input type="text" value="---"/>	Frequency <input type="text" value="medium"/>
Video reference <input type="text" value="---"/>	

Group A	Group B																																																																																
<p>TRUNK</p> <table border="1" style="width: 100%; border-collapse: collapse;"> <tr> <td style="padding: 2px;">Flexion > 60°</td> <td style="text-align: center; font-size: 24px; font-weight: bold;">5</td> </tr> <tr> <td style="padding: 2px;">Rot. <input checked="" type="checkbox"/></td> <td></td> </tr> <tr> <td style="padding: 2px;">Lateral tilt <input type="checkbox"/></td> <td style="text-align: center; font-size: 12px;">6</td> </tr> </table> <p>NECK</p> <table border="1" style="width: 100%; border-collapse: collapse;"> <tr> <td style="padding: 2px;">Flexion > 20°</td> <td style="text-align: center; font-size: 24px; font-weight: bold;">3</td> </tr> <tr> <td style="padding: 2px;">Rot. <input checked="" type="checkbox"/></td> <td></td> </tr> <tr> <td style="padding: 2px;">Lateral tilt <input type="checkbox"/></td> <td style="text-align: center; font-size: 12px;">3</td> </tr> </table> <p>LEGS</p> <table border="1" style="width: 100%; border-collapse: collapse;"> <tr> <td style="padding: 2px;">Bilateral support</td> <td></td> </tr> <tr> <td style="padding: 2px;">Knee flex. 30-60° <input checked="" type="checkbox"/></td> <td></td> </tr> <tr> <td style="padding: 2px;">>60° <input type="checkbox"/></td> <td style="text-align: center; font-size: 12px;">4</td> </tr> </table> <table style="width: 100%;"> <tr> <td style="text-align: right; padding-right: 10px;">Table A</td> <td style="text-align: center; font-size: 24px; font-weight: bold;">8</td> </tr> <tr> <td></td> <td style="text-align: center; font-size: 24px; font-weight: bold;">+</td> </tr> <tr> <td style="padding: 2px;">FORCE / LOAD</td> <td></td> </tr> <tr> <td style="padding: 2px;">< 5 kg</td> <td style="text-align: center; font-size: 12px;">0</td> </tr> <tr> <td style="padding: 2px;">Sudden or abrupt force <input type="checkbox"/></td> <td style="text-align: center; font-size: 12px;">3</td> </tr> <tr> <td></td> <td style="text-align: center; font-size: 24px; font-weight: bold;">=</td> </tr> <tr> <td style="text-align: right; padding-right: 10px;">Score A</td> <td style="text-align: center; font-size: 24px; font-weight: bold;">8</td> </tr> </table>	Flexion > 60°	5	Rot. <input checked="" type="checkbox"/>		Lateral tilt <input type="checkbox"/>	6	Flexion > 20°	3	Rot. <input checked="" type="checkbox"/>		Lateral tilt <input type="checkbox"/>	3	Bilateral support		Knee flex. 30-60° <input checked="" type="checkbox"/>		>60° <input type="checkbox"/>	4	Table A	8		+	FORCE / LOAD		< 5 kg	0	Sudden or abrupt force <input type="checkbox"/>	3		=	Score A	8	<p>ARM</p> <table border="1" style="width: 100%; border-collapse: collapse;"> <tr> <th style="width: 50%; text-align: center;">Right</th> <th style="width: 50%; text-align: center;">Left</th> </tr> <tr> <td style="padding: 2px;">Flexion 20-45°</td> <td style="padding: 2px;">Flexion 45-90°</td> </tr> <tr> <td style="padding: 2px;">Abduct. <input type="checkbox"/></td> <td style="padding: 2px;">Abduct. <input checked="" type="checkbox"/></td> </tr> <tr> <td style="padding: 2px;">Rotation <input checked="" type="checkbox"/></td> <td style="padding: 2px;">Rotation <input type="checkbox"/></td> </tr> <tr> <td style="text-align: center; font-size: 24px; font-weight: bold;">6</td> <td style="text-align: center; font-size: 24px; font-weight: bold;">4</td> </tr> <tr> <td style="padding: 2px;">Shoulder raised <input type="checkbox"/></td> <td style="padding: 2px;">Shoulder raised <input type="checkbox"/></td> </tr> <tr> <td style="padding: 2px;">Supported/in favor of gravity <input type="checkbox"/></td> <td style="padding: 2px;">Supported/in favor of gravity <input type="checkbox"/></td> </tr> </table> <p>FOREARM</p> <table border="1" style="width: 100%; border-collapse: collapse;"> <tr> <td style="padding: 2px;">Flexion 60-100°</td> <td style="text-align: center; font-size: 24px; font-weight: bold;">1</td> </tr> <tr> <td style="padding: 2px;"></td> <td style="text-align: center; font-size: 12px;">2</td> </tr> <tr> <td style="padding: 2px;">Flexion < 60°</td> <td style="text-align: center; font-size: 24px; font-weight: bold;">2</td> </tr> <tr> <td style="padding: 2px;"></td> <td style="text-align: center; font-size: 12px;">2</td> </tr> </table> <p>WRIST</p> <table border="1" style="width: 100%; border-collapse: collapse;"> <tr> <td style="padding: 2px;">Flexion/Extension 0-15°</td> <td style="text-align: center; font-size: 24px; font-weight: bold;">1</td> </tr> <tr> <td style="padding: 2px;">Rot. <input type="checkbox"/></td> <td></td> </tr> <tr> <td style="padding: 2px;">Lateral dev. <input type="checkbox"/></td> <td style="text-align: center; font-size: 12px;">3</td> </tr> <tr> <td style="padding: 2px;">Flexion/Extension > 15°</td> <td style="text-align: center; font-size: 24px; font-weight: bold;">2</td> </tr> <tr> <td style="padding: 2px;">Rot. <input type="checkbox"/></td> <td></td> </tr> <tr> <td style="padding: 2px;">Lateral dev. <input type="checkbox"/></td> <td style="text-align: center; font-size: 12px;">3</td> </tr> </table> <table style="width: 100%;"> <tr> <td style="text-align: right; padding-right: 10px;">Table B</td> <td style="text-align: center; font-size: 24px; font-weight: bold;">6</td> </tr> <tr> <td></td> <td style="text-align: center; font-size: 24px; font-weight: bold;">+</td> </tr> <tr> <td style="padding: 2px;">COUPLING</td> <td></td> </tr> <tr> <td style="padding: 2px;">Good</td> <td style="text-align: center; font-size: 12px;">0</td> </tr> <tr> <td></td> <td style="text-align: center; font-size: 12px;">3</td> </tr> <tr> <td></td> <td style="text-align: center; font-size: 24px; font-weight: bold;">=</td> </tr> <tr> <td style="text-align: right; padding-right: 10px;">Score B</td> <td style="text-align: center; font-size: 24px; font-weight: bold;">6</td> </tr> </table>	Right	Left	Flexion 20-45°	Flexion 45-90°	Abduct. <input type="checkbox"/>	Abduct. <input checked="" type="checkbox"/>	Rotation <input checked="" type="checkbox"/>	Rotation <input type="checkbox"/>	6	4	Shoulder raised <input type="checkbox"/>	Shoulder raised <input type="checkbox"/>	Supported/in favor of gravity <input type="checkbox"/>	Supported/in favor of gravity <input type="checkbox"/>	Flexion 60-100°	1		2	Flexion < 60°	2		2	Flexion/Extension 0-15°	1	Rot. <input type="checkbox"/>		Lateral dev. <input type="checkbox"/>	3	Flexion/Extension > 15°	2	Rot. <input type="checkbox"/>		Lateral dev. <input type="checkbox"/>	3	Table B	6		+	COUPLING		Good	0		3		=	Score B	6
Flexion > 60°	5																																																																																
Rot. <input checked="" type="checkbox"/>																																																																																	
Lateral tilt <input type="checkbox"/>	6																																																																																
Flexion > 20°	3																																																																																
Rot. <input checked="" type="checkbox"/>																																																																																	
Lateral tilt <input type="checkbox"/>	3																																																																																
Bilateral support																																																																																	
Knee flex. 30-60° <input checked="" type="checkbox"/>																																																																																	
>60° <input type="checkbox"/>	4																																																																																
Table A	8																																																																																
	+																																																																																
FORCE / LOAD																																																																																	
< 5 kg	0																																																																																
Sudden or abrupt force <input type="checkbox"/>	3																																																																																
	=																																																																																
Score A	8																																																																																
Right	Left																																																																																
Flexion 20-45°	Flexion 45-90°																																																																																
Abduct. <input type="checkbox"/>	Abduct. <input checked="" type="checkbox"/>																																																																																
Rotation <input checked="" type="checkbox"/>	Rotation <input type="checkbox"/>																																																																																
6	4																																																																																
Shoulder raised <input type="checkbox"/>	Shoulder raised <input type="checkbox"/>																																																																																
Supported/in favor of gravity <input type="checkbox"/>	Supported/in favor of gravity <input type="checkbox"/>																																																																																
Flexion 60-100°	1																																																																																
	2																																																																																
Flexion < 60°	2																																																																																
	2																																																																																
Flexion/Extension 0-15°	1																																																																																
Rot. <input type="checkbox"/>																																																																																	
Lateral dev. <input type="checkbox"/>	3																																																																																
Flexion/Extension > 15°	2																																																																																
Rot. <input type="checkbox"/>																																																																																	
Lateral dev. <input type="checkbox"/>	3																																																																																
Table B	6																																																																																
	+																																																																																
COUPLING																																																																																	
Good	0																																																																																
	3																																																																																
	=																																																																																
Score B	6																																																																																
<table style="width: 100%;"> <tr> <td style="text-align: right; padding-right: 10px;">Table C</td> <td style="text-align: center; font-size: 24px; font-weight: bold;">10</td> </tr> <tr> <td></td> <td style="text-align: center; font-size: 24px; font-weight: bold;">+</td> </tr> <tr> <td style="padding: 2px;">ACTIVITY</td> <td></td> </tr> <tr> <td style="padding: 2px;">Static (sustained > 1 min) <input type="checkbox"/></td> <td style="text-align: center; font-size: 12px;">0</td> </tr> <tr> <td style="padding: 2px;">Repeated (>4 times/min) <input type="checkbox"/></td> <td style="text-align: center; font-size: 12px;">3</td> </tr> <tr> <td style="padding: 2px;">Postural changes/unstable base <input type="checkbox"/></td> <td style="text-align: center; font-size: 12px;">4</td> </tr> <tr> <td></td> <td style="text-align: center; font-size: 24px; font-weight: bold;">=</td> </tr> <tr> <td style="text-align: right; padding-right: 10px;">REBA Score</td> <td style="text-align: center; font-size: 24px; font-weight: bold;">10</td> </tr> </table> <table style="width: 100%;"> <tr> <td style="padding: 2px;">Risk Level</td> <td style="text-align: center; background-color: #ff6600; color: white; padding: 5px;">High</td> </tr> <tr> <td style="padding: 2px;">Action Level</td> <td style="text-align: center; padding: 5px;">Necessary soon</td> </tr> </table>		Table C	10		+	ACTIVITY		Static (sustained > 1 min) <input type="checkbox"/>	0	Repeated (>4 times/min) <input type="checkbox"/>	3	Postural changes/unstable base <input type="checkbox"/>	4		=	REBA Score	10	Risk Level	High	Action Level	Necessary soon																																																												
Table C	10																																																																																
	+																																																																																
ACTIVITY																																																																																	
Static (sustained > 1 min) <input type="checkbox"/>	0																																																																																
Repeated (>4 times/min) <input type="checkbox"/>	3																																																																																
Postural changes/unstable base <input type="checkbox"/>	4																																																																																
	=																																																																																
REBA Score	10																																																																																
Risk Level	High																																																																																
Action Level	Necessary soon																																																																																

Figure 9: Postures [REBA] – Report (detail of the posture)

REDESIGN

The evaluator can use the results window to see how the different scores change as the encoding variables are modified. This can be helpful when redesigning the task or workstation to reduce the risk of a particular posture.

In order to avoid losing the data of the original posture, it is advisable to backup the posture, rename it as a redesign, edit the relevant changes and save it.

In general, we will try to reduce those scores that are closest to its *maximum possible value*. For example, the posture "store clothes on the shelf" (see Figures 3, 4 and 5), has a *REBA score* of 10, which implies a high level of risk, and action is necessary soon (Figure 6). In this case, we can observe that the *activity* is not influencing, the *score A* is closer to its maximum than *score B*, which depends mainly on the trunk and neck (both cells are at their maximum value, 5 and 3, respectively) since the *force/load* is not affecting.

Figure 10 shows a possible redesign of this posture, where the trunk flexion has been reduced (flexion of 20-60°, instead of > 60°), and the trunk and neck rotations have been eliminated. Figure 11 shows the results obtained after these changes: in group A, the scores for the trunk (5 to 3) and neck (3 to 2) have decreased, which results in a *REBA score* of 7 and a medium risk level, action being necessary to reduce the risk. Obviously, the redesign process can continue until the desired risk level is achieved.




Figure 10: Postures [REBA] – Example of redesign (trunk and neck changes)




Figure 11: Postures [REBA] – Example of redesign (new results)